
## **Steps to Configure and Verify DHCP Server in Cisco Packet Tracer:**

**Step 1:** First, open the cisco packet tracer desktop and select the devices given below:

| S.NO | Device | Model-Name | Unit |
|------|--------|------------|------|
| 1.   | PC     | PC         | 5    |
| 2.   | Switch | PT-Switch  | 2    |
| 3.   | Router | PT-Router  | 1    |
| 4.   | Server | Server-PT  | 1    |


- Now create a network topology as shown below the image.
- Use an Automatic connecting cable to connect the devices with others.



**Step 2:** Configure the Server with IPv4 address and Subnet Mask according to the Data given above.

- To assign an IP address in Server, click on Server-PT.
- Then, go to desktop and IP configuration and there you will find IPv4 configuration.
- Add IPv4 address, subnet mask, and Default Gateway.

| Parameters      | Address value |  |
|-----------------|---------------|--|
| IPv4 Address    | 172.168.10.2  |  |
| Subnet Mask     | 255.255.255.0 |  |
| Default-Gateway | 172.168.10.1  |  |




Ignore the option below if you have completed the configuration above.

**Option 2.** Assigning IP address using the ipconfig command.

- We can also assign an IP address with the help of a command.
- Go to the command prompt of the server
- Then, type ipconfig <IPv4 address><subnet mask><default gateway>(if needed)

example: ipconfig 172.168.10.2 255.255.255.0 172.168.10.1





**Step 3:** Configuring the DHCP server.

To configure the DHCP server first,

- Click on Server then, Go to services.
- Click on DHCP and turn on the services and configure the DHCP server with the help of the data given below.
  - Delete the default values of Start IP Address and subnet Mask then save the info.
  - o Create two new pools.

POOL1 and POOL2 and fill in the data as shown in the images below.





**Step 4:** Configuring Router with IPv4 Address and Subnet Mask.


## **IP Addressing Table for Router:**

| S.NO | Device  | Interface       | IPv4 Address | Subnet Mask   |
|------|---------|-----------------|--------------|---------------|
| 1.   | router0 | FastEthernet0/0 | 172.168.10.1 | 255.255.255.0 |
|      |         | FastEthernet0/1 | 192.168.10.1 | 255.255.255.0 |

- To assign an IP address in router0, click on router0.
- Then, go to config and then Interfaces, and make sure to turn on the ports.
- Then, configure the IP address in FastEthernet according to IP addressing Table.
- Fill IPv4 address and subnet mask.

**Step 5:** Configuring the PCs and changing the IP configuration.

- To assign an IP address in PC0, click on PC0.
- Then, go to desktop and IP configuration and there you will find IPv4 configuration.
- Change its state from static to DHCP.
- It will automatically fetch the data and configure itself.



• Repeat the same procedure with other PCs to configure them thoroughly.